

5 Minute Transformation Protocol

Overview

The following protocol results in only 10% efficiency compared to the High Efficiency Transformation Protocol. Perform steps 1-6 in the tube provided.

Protocol

1. Remove cells from -80°C freezer and thaw in your hand.
2. Add 1-5 μl containing 1 pg-100 ng of plasmid DNA to the cell mixture. Carefully flick the tube 4-5 times to mix cells and DNA. **Do not vortex.**
3. Place the mixture on ice for 2 minutes. Do not mix.
4. Heat shock at exactly 42°C for exactly 30 seconds. Do not mix.
5. Place on ice for 2 minutes. Do not mix.
6. Pipette 250 μl of room temperature SOC into the mixture. Immediately spread 50-100 μl onto a selection plate and incubate overnight at $37-42^{\circ}\text{C}$. NOTE: Selection using antibiotics other than ampicillin may require some outgrowth before plating on selective media. Colonies develop faster at temperatures above 37°C , however some constructs may be unstable at elevated temperatures.